

# Install and Configure OpenVPN Client

## Install OpenVPN client

```
apt install openvpn -y
```

## Manually connect to OpenVPN server

- Generate .ovpn file on OpenVPN server and copy to OpenVPN client machine
- Run the command below to connect:

```
openvpn --config client.ovpn
```

## Automatically connect to OpenVPN server

- Generate .ovpn file on OpenVPN server and copy to OpenVPN client machine under /etc/openvpn directory as a .conf file. For example, if you have a my-server.ovpn file you would run the following command:

```
cp my-server.ovpn /etc/openvpn/my-server.conf
```

- Create credentials file in /etc/openvpn/my-server-creds.txt

```
vi /etc/openvpn/my-server-creds.txt
```

- Enter the username and password each one in a separate line like below:

```
openvpn_username  
somepassword
```

- Save the file
- Edit /etc/openvpn/my-server.conf file:

```
vi /etc/openvpn/my-server.conf
```

- Locate the **auth-user-pass** line in the file and add the credentials file filename next to it like below:

```
...  
auth-user-pass my-server-creds.txt  
...
```

- Save the file
- Edit /etc/default/openvpn:

```
vi /etc/default/openvpn
```

- Uncomment the following line (remove the **#** from the front) :

```
AUTOSTART="all"
```

- Save the file
- Restart the OpenVPN service on the OpenVPN client:

```
systemctl restart openvpn
```

- Reboot the OpenVPN Client server and ensure it connects automatically

---

Revision #1

Created 17 November 2020 18:51:03 by Dino Edwards

Updated 17 November 2020 18:52:14 by Dino Edwards