

Relay Domains

In order for Hermes SEG to deliver email, you must first set the domain(s) that Hermes SEG will process email for along with their corresponding email server(s). You can add as many domains and email servers as required. An email server can be configured as an IP address or a Host Name as long as the Hermes SEG can reach it over Port TCP/25. Multiple domains can be pointed to the same email server if necessary.

Add Relay Domain with IP Address Destination

1. Under the **Relay Domain Destination Type**, select the **IP Address Destination** option.
2. In the **Relay Domain** field enter the domain name and in the **Dest IP** fields, enter the email server's IP address and click the **Add** button (**Figure 1**).

Figure 1

Administration Console Firewall Settings

Your IP Address is: 192.168.1.100

Firewall Status

- ☒ **Enabled** (Only Specified IP Addresses Allowed. **DO NOT Enable unless your IP Address is allowed**)
- ☐ **Disabled** (All IP Addresses Allowed)

Save Settings

3. After adding a Relay Domain and IP Address Destination, the entry will show up below the **Edit/Delete domains & Destinations** section (**Figure 2**).

Figure 2

Edit/Delete Domains & Destinations

Domain	Destination	Edit	Delete
domain.tld	192.168.0.100		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.1		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.100		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.100		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.1		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.100		Cannot delete. Must remove existing internal recipients assigned to domain
domain.tld	192.168.0.100		✗
domain.tld	192.168.0.100		✗

Add Relay Domain with Host Name Destination

1. Under the **Relay Domain Destination Type**, select the **Host Name Destination** option.
2. In the **Relay Domain** field enter the domain name, in the **Dest Host Name** field, enter the email server's Host Name part of the FQDN address (without the domain part), in the **Dest Host Domain** field, enter the email server's domain part of the FQDN address and then click the **Add** button (**Figure 3**).

Figure 3

Advanced Search

Search Mode	Search Text 1	Search Text 2
DATE/TIME ONLY		
Start Date	Start Time	End Date
3/1/2017	10:15 AM	6/15/2017
End Time		
11:59 PM	Go	

Displaying 1 through 100 out of 627086 total Entries.













[Next 100 Entries >>](#)

Date/Time	Message	Facility
06/15/2017 23:59:51	7FA6140C08: to=, relay=hdgexchange.deeztek.com[192.168.40.201]:25, delay=3.3, delays=0.01/0.02 /0/3.3, dsn=2.6.0, status=sent (250 2.6.0 <20170616040005.12EEB402C3@smtp.glaucomaexpert.com> [InternalId=34084] Queued mail for delivery)	SMTP CLIENT
06/15/2017 23:59:48	Host offered STARTTLS: [hdgexchange.deeztek.com]	SMTP CLIENT
06/15/2017 23:59:48	disconnect from localhost[127.0.0.1]	SMTP SERVICE
06/15/2017 23:59:48	7FA6140C08: from=, size=1598, nrcpt=1 (queue active)	QUEUE SERVICE
06/15/2017 23:59:48	7FA6140C08: client=localhost[127.0.0.1], orig_client=smtp.glaucomaexpert.com[74.92.146.137]	SMTP SERVICE
06/15/2017 23:59:48	7FA6140C08: message-id=<20170616040005.12EEB402C3@smtp.glaucomaexpert.com>	SMTP CLEANUP SERVICE
06/15/2017 23:59:48	4790840BCC: removed	QUEUE SERVICE
06/15/2017 23:59:48	connect from localhost[127.0.0.1]	SMTP SERVICE
06/15/2017 23:59:48	4790840BCC: to=, relay=127.0.0.1[127.0.0.1]:10021, delay=1.2, delays=0.04/0.02/0/1.1, dsn=2.6.0, status=sent (250 2.6.0 from MTA(smtp:[127.0.0.1]:10025): 250 2.6.0 Message received)	SMTP CLIENT

- After adding a Relay Domain and Host Name Destination, the entry will show up below the **Edit/Delete domains & Destinations** section (**Figure 4**).

Figure 4

Edit/Delete Domains & Destinations

Domain	Destination	Edit	Delete
domain1.com	hdgexchange.deeztek.com		Cannot delete. Must remove existing internal recipients assigned to domain
domain2.com	192.168.100		Cannot delete. Must remove existing internal recipients assigned to domain
domain3.com	hdgexchange.deeztek.com		Cannot delete. Must remove existing internal recipients assigned to domain
domain4.com	74.92.146.137		Cannot delete. Must remove existing internal recipients assigned to domain
domain5.com	74.92.146.137		Cannot delete. Must remove existing internal recipients assigned to domain
domain6.com	hdgexchange.deeztek.com		Cannot delete. Must remove existing internal recipients assigned to domain
domain7.com	192.168.100		
domain.tld	192.168.0.100		
domain2.tld	server.domain.tld		

Edit Existing Relay Domain Mapping

- Click on the edit icon  under the **Edit** column of the **Domain** you wish to edit.

2. On the **Edit Existing Relay Domain Mapping** page, select either the **IP Address Destination** or the **Host Name Destination** option (**Figure 5**).

Figure 5

Edit Existing Relay Domain Mapping

Select the type of Destination you are adding and then fill out the corresponding information in the fields below.

- ☒ IP Address Destination
- ☐ Host Name Destination

IP Address Destination

Selecting **IP Address Destination** will enable the IP Address Destination entry. Enter the IP Address of the destination email server under the **Dest IP** field and click the **Edit** button to save your changes (**Figure 6**). Note that the **Relay Domain** field is already pre-filled and cannot be changed.

Figure 6

Edit Existing Relay Domain Mapping

Select the type of Destination you are adding and then fill out the corresponding information in the fields below.

- ☒ IP Address Destination
- ☐ Host Name Destination

IP Address Destination

Relay Domain

domain.tld

Dest IP

. . .

Host Name Destination

Selecting Host name Destination will enable the Host Name Destination entry. Enter the host name (without the domain) of the destination email server under the **Dest Host Name** field, enter the domain of the destination email server under the **Dest Host Domain** field and click the **Edit** button to save your changes (**Figure 7**). Note that the **Relay Domain** field is already pre-filled and cannot be changed.

Figure 7

Edit Existing Relay Domain Mapping

Select the type of Destination you are adding and then fill out the corresponding information in the fields below.

- ☐ IP Address Destination
- ☒ Host Name Destination

IP Address Destination

Relay Domain

domain.tld

Dest IP

Edit

Host Name Destination

Relay Domain

domain.tld

Dest Host Name

Dest Host Domain

Edit

3. When finished making your changes, click on the **Back to Relay Domains** button on the bottom of the page to return to the **Relay Domains** page (**Figure 8**).

Figure 8

Back to Relay Domains

Delete Existing Relay Domain Mapping

Note: Deleting existing Relay Domain mappings can only be accomplished if there are no existing Internal Recipients assigned to that domain. If there are existing Internal Recipients assigned to the domain, you will receive the following message under the Delete column of the Edit/Delete Domains & Destination section (**Figure 9**). In order to delete the domain, you must first navigate to Gateway --> Internal Recipients, delete all the Internal Recipients for that domain and then return to this section to delete the domain.

Figure 9

Edit/Delete Domains & Destinations

Domain	Destination	Edit	Delete
helenstokely.com	helenstokely.com		Cannot delete. Must remove existing internal recipients assigned to domain
brimphillips.com	brimphillips.com		Cannot delete. Must remove existing internal recipients assigned to domain
lancasterfarm.com	lancasterfarm.com		Cannot delete. Must remove existing internal recipients assigned to domain
commsconstruction.com	commsconstruction.com		Cannot delete. Must remove existing internal recipients assigned to domain
osmoplyre.com	osmoplyre.com		Cannot delete. Must remove existing internal recipients assigned to domain
uep.com.au	uep.com.au		Cannot delete. Must remove existing internal recipients assigned to domain
steelefirst.com	steelefirst.com		


1. Click on the  icon under the Delete column of the Domain you wish to delete.
2. On the confirmation page, click on the **Yes** button to proceed with deleting the domain.
Clicking on the **No** button will take you back to the **Relay Domains** page (**Figure 10**).

Figure 10

Are you sure you want to delete this Relay Domain?

YES

NO

Revision #1

Created 23 November 2020 19:17:09 by Dino Edwards

Updated 28 June 2022 17:05:17 by Dino Edwards